

INTELLICAT[®] INSTALLATION KIT

Manual Part Number: 99875187-6

OCTOBER 2004

MAGTEK[®]
REGISTERED TO ISO 9001:2000

1710 Apollo Court
Seal Beach, CA 90740
Phone: (562) 546-6400
FAX: (562) 546-6301
Technical Support: (651) 415-6800
www.magtek.com

Information in this document is subject to change without notice. No part of this document may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose, without the express written permission of MagTek, Inc.

MagTek is a registered trademark of MagTek, Inc.
 IntelliCAT® is a registered trademark of MagTek, Inc.
 IntelliPIN® is a registered trademark of MagTek, Inc.
 IntelliCoder™ is a trademark of MagTek, Inc.

REVISIONS

Rev Number	Date	Notes
1	23 Jan 01	Initial Release contains the following: 99875172 99875182 99875183 99875184
2	27 Mar 01	Updated 99875172 -2 to -3; Updated 99875183 -1 to -2; Updated 99875184 -1 to -2 Added 99875189 -1
3	25 Apr 01	Updated 99875189 to -2
4	27 May 03	Front Matter: Added ISO line to logo. Updated all enclosures.
5	3 Mar 04	Throughout: Changed IntelliCAT text and forms to IntelliCAT® (registered) where required. Updated all enclosures: 99875172 to -7 99875182 to -3 99875183 to -5 99875184 to -4 99875189 to -4
6	6 Oct 04	Removed 99875189, Timeline – obsolete.

TABLE OF CONTENTS

INTELLICAT® SOFTWARE SUITE LICENSE AND MAINTENANCE AGREEMENT.....	iv
INTELLICAT® SYSTEM INSTALLATION OVERVIEW.....	1
INTELLICAT® WORKSTATION INSTALLATION.....	3
INTELLICAT® WORKSTATION INSTALLATION.....	4
INTELLICAT® DESIGNER WORKSHEET	5
INTELLICAT® DESIGNER WORKSHEET	6



REGISTERED TO ISO 9001:2000

1710 Apollo Court, Seal Beach, CA 90740

Voice: 562-546-6400 Fax: 562-546-6301

Part Number 99875187-6

13 Jan 2005

INTELLICAT[®] SOFTWARE SUITE LICENSE AND MAINTENANCE AGREEMENT

IMPORTANT: YOU SHOULD CAREFULLY READ ALL THE TERMS, CONDITIONS AND RESTRICTIONS OF THIS LICENSE AGREEMENT BEFORE INSTALLING THE SOFTWARE PACKAGE. YOUR INSTALLATION OF THE SOFTWARE PACKAGE PRESUMES YOUR ACCEPTANCE OF THE TERMS, CONDITIONS, AND RESTRICTIONS CONTAINED IN THIS AGREEMENT. IF YOU DO NOT AGREE WITH THESE TERMS, CONDITIONS, AND RESTRICTIONS, PROMPTLY RETURN THE SOFTWARE PACKAGE AND ASSOCIATED DOCUMENTATION TO ABOVE ADDRESS ATTENTION: CUSTOMER SUPPORT.

TERMS, CONDITIONS AND RESTRICTIONS

MagTek, Incorporated (the "Licensor") owns and has the right to distribute the described software and documentation, collectively referred to as the "Software".

LICENSE: In consideration for the license fee Licensor grants you (the "Licensee") the right to use the Software in conjunction with MagTek Motorized IntelliCoder[®] and IntelliPIN[®] products, and other MagTek approved Card Personalization Devices here after referred to as "CPD". A separate Software License fee and separate Software Maintenance fee is required for each Motorized IntelliCoder or CPD Licensee purchases.

LICENSEE MAY NOT COPY, MODIFY OR TRANSFER THE SOFTWARE IN WHOLE OR IN PART EXCEPT AS EXPRESSLY PROVIDED IN THIS AGREEMENT. Licensee may not decompile, disassemble or in any other manner attempt to reverse engineer the Software. Licensee shall not tamper with, bypass or alter any security features of the software or attempt to do so.

By accepting this Software License the Licensee agrees to pay an annual Software Maintenance fee per published schedule. This fee will be automatically billed to the Licensee and will afford the Licensee on-going Software support and any future upgrades without additional charges.

TRANSFER: Licensee may not transfer the Software or license to the Software to another party without prior written authorization of the Licensor. If Licensee transfers the Software without authorization, all rights granted under this Agreement are automatically terminated.

COPYRIGHT: The Software is copyrighted. Licensee may not copy the Software except for archival purposes or to load for execution purposes. All other copies of the Software are in violation of this Agreement.

TERM: This Agreement is in effect as long as Licensee continues the use of the Software. The Licensor also reserves the right to terminate this Agreement if Licensee fails to comply with any of the terms, conditions or restrictions contained herein. Should Licensor terminate this Agreement due to Licensee's failure to comply, Licensee agrees to return the Software to Licensor. Receipt of a returned Software by the Licensor shall mark the termination of future billing for any applicable Software maintenance charges, but shall not terminate any obligation on behalf of Licensee for Software maintenance charges due and payable.

LIMITED WARRANTY: Licensor warrants to the Licensee that the disk(s) on which the Software is recorded to be free from defects in material or workmanship under normal use for a period of ninety (90) days from the date of initial purchase. THE SOFTWARE IS PROVIDED AS IS WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. Because of the diversity of conditions and PC hardware under which the Software may be used, Licensor does not warrant that the Software will meet Licensee specifications or that the operation of the Software will be uninterrupted or free of errors.

IN NO EVENT WILL LICENSOR BE LIABLE FOR ANY DAMAGES, INCLUDING ANY LOST PROFITS, LOST SAVINGS OR OTHER INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE SOFTWARE. Licensee's sole remedy in the event of a defect in material or workmanship is expressly limited to replacement of the Software disk(s).

GOVERNING LAW: If any provision of this Agreement is found to be unlawful, void or unenforceable, that provision shall be removed from consideration under this Agreement and will not affect the enforceability of any of the remaining provisions. This Agreement shall be governed by the laws of the State of California and shall insure to the benefit of MagTek, Incorporated, its successors or assigns.

ACKNOWLEDGMENT: LICENSEE ACKNOWLEDGES THAT HE HAS READ THIS AGREEMENT, UNDERSTANDS ALL OF ITS TERMS, CONDITIONS AND RESTRICTIONS AND AGREES TO BE BOUND BY THEM. LICENSEE ALSO AGREES THAT THIS AGREEMENT SUPERSEDES ANY AND ALL, VERBAL AND WRITTEN, COMMUNICATIONS BETWEEN LICENSOR AND LICENSEE OR THEIR ASSIGNS RELATING TO THE SUBJECT MATTER OF THIS AGREEMENT.

QUESTIONS REGARDING THIS AGREEMENT SHOULD BE ADDRESSED IN WRITING TO MAGTEK, INCORPORATED, ATTENTION: CUSTOMER SUPPORT, AT THE ABOVE ADDRESS OR E-MAILED TO support@magtek.com


INTENTIONALLY LEFT BLANK FOR REPRODUCING TWO-SIDED FORMS

INTELLICAT® SYSTEM INSTALLATION OVERVIEW

Implementation Coordinator: _____


Module	Purpose	Comments	Financial Institution Contact	Number of Activation Codes
Administrator	<ul style="list-style-type: none"> Controls access to IntelliCAT Assign new operators Assign operator security level Make operator cards Generates a database that is shared by other modules 	<p>It is recommended that this be installed in a secure manner where only authorized personnel have access.</p> <ol style="list-style-type: none"> Requires IntelliCoder™ or Embosser to generate operator cards. Usually installed only on a single PC that is accessible to an administrator or supervisor. 	<p>Name: _____</p> <p>e-mail: _____</p> <p>Phone: _____</p>	
Key Injection	<ul style="list-style-type: none"> Loads all necessary keys into IntelliPIN® Assigns identifier to each key (0-5, A-Z, a-z) Changes master key in IntelliPIN prior to deployment 	<p>Security Issues:</p> <ol style="list-style-type: none"> Should not be on the network. Should be used in a secure room. 	<p>Name: _____</p> <p>e-mail: _____</p> <p>Phone: _____</p>	
Designer	<ul style="list-style-type: none"> Creates card templates and track layouts used in the Data Entry module. Designer templates (CRD files) define what cards are accepted by the IntelliCAT system and what actions may be performed on these cards. CRD files are distributed to each workstation with Data Entry Module. 	<ol style="list-style-type: none"> Defines PAN/VAN, algorithms and placement of all variables. Defines which keys are used (0-5, A-Z, a-z) for each encryption operation. Normally used in a single PC, either standalone or on a network. 	<p>Name: _____</p> <p>e-mail: _____</p> <p>Phone: _____</p>	
Controller	<ul style="list-style-type: none"> Processes Card Production Requests. Controls card activity at the IntelliCoder or embosser through the use of a "Print" queue. 	<ol style="list-style-type: none"> Only required in a network installation. It would be loaded only on the workstation that has an IntelliCoder or embosser directly attached. 	<p>Name: _____</p> <p>e-mail: _____</p> <p>Phone: _____</p>	
Data Entry	<ul style="list-style-type: none"> Acquires cardholder information Issues cards Re-PIN cards 	<ol style="list-style-type: none"> Used with IntelliPIN attached to PC. In a non-network installation, IntelliCoder or Embosser may be attached. 	<p>Name: _____</p> <p>e-mail: _____</p> <p>Phone: _____</p>	
Configuration	<ul style="list-style-type: none"> Change configuration Modify operational paths Maintain network installations Modify location of installed components 	<p>This module automatically installed on each PC. During installation, if module placement is not known, accept the defaults. This will speed up the installation, and later the Configuration module can modify the defaults.</p>	<p>MAGTEK® REGISTERED TO ISO 9001:2000 1710 Apollo Court Seal Beach, CA 90740 Phone: (562) 564-6400; FAX: (562) 546-6301 Technical Support: (888) 624-8350 www.maatek.com</p>	

The following illustration shows a possible non-network PC installation:




Non-network Installation

The following illustration shows the Key Injection Workstation. It should never be on a network.



Key Injection Installation

The following illustration shows a possible network installation:




Network Installation

INTELLICAT® WORKSTATION INSTALLATION

Financial Institution: _____

Branch: _____

Workstation: _____



IntelliCAT Software Suite CD Serial Number _____

On the form below, indicate which module(s) should be installed on this workstation. The Activation Codes will be filled in by the installer after the modules have been installed.

Challenge _____

Install if checked	Module Name	Activation Code
	Administrator module	
	Controller module	
	Data Entry module	
	Designer module	
	Key Injection module	

Installation Notes:

- 1) Insert the CD and, when prompted, use the cursor to place a check mark next to each module that is indicated in the table above.
- 2) Refer to the back of this document for a list of all of the setup values and paths that need to be entered for this workstation.
- 3) After the installation is complete, attempt to open each module which has been installed.
- 4) When the challenge is displayed, call the Mag-Tek help desk (888-624-8350) to obtain an activation code for each installed module. You will be required to enter this activation code in order to operate each module.

INTELLICAT® WORKSTATION INSTALLATION

As the installation progresses, answer the questions as indicated below. Not all of the entries will be used in every installation.

Question	MagTek Default	Actual
Executables path	C:\Program Files\MagTek\IntelliCAT\	
Modules to install	_Administrator module _Designer module _Controller module _Key Injection module _Data Entry module	
Select Program Folder	Mag-Tek\IntelliCAT System	
CPD's to make available	_DataCard_150i _Motorized IntelliCoder _IntelliCAT_Controller _PIN w/o Card _IntelliCoder	
CPD for Customer cards	_IntelliCoder (local connection) _Motorized IntelliCoder _PIN w/o Card _PIN w/o Card	
COM Port for Customer card device	2	
Operator Timeout value	15 minutes	
Data Entry Transaction Mode	_Yes, one transaction per Operator Log On _No, use the automatic time out	
IntelliPIN Timeout	30 seconds	
CPD for Administrator	_IntelliCAT_Controller (print via Queue) _DataCard_150i Embosser (local connection) _IntelliCoder (local connection) _Motorized IntelliCoder (local connection)	
COM Port Number: Administrator CPD	2	
COM Port Numbers: IntelliPIN	1	
Operator's Database path	C:\Program Files\MagTek\IntelliCAT\	
History Path	C:\Program Files\MagTek\IntelliCAT\History	
Card Layout Path	C:\Program Files\MagTek\IntelliCAT\Card Layouts	
Controller List Path	C:\Program Files\MagTek\IntelliCAT\	
Report Path	C:\Program Files\MagTek\IntelliCAT\Reports	
BIN List.txt Path	C:\Program Files\MagTek\IntelliCAT\BinList.txt	
Controller Information	Default Controller	
Controller Queue Path	C:\Program Files\MagTek\IntelliCAT\Queue	
Controller Working Path	C:\Program Files\MagTek\IntelliCAT\	
Would you like a short-cut to IntelliCAT folder on desktop	Yes	

After the installation has completed, if you are asked to restart the computer, select “Yes, I want to restart my computer now.”

Part Number: 99875183-5
3 Mar 2004

MAGTEK®
REGISTERED TO ISO 9001:2000

1710 Apollo Court
Seal Beach, CA 90740
Phone: (562) 546-6400
FAX: (562) 546-6301
Technical Support: (888) 624-8350
www.maatek.com

